

POP3 File Reader

Checks for messages on a specified POP3 account. Pulls the next unread message, extracts any attached files, and passes them on to the next Jitterbit processing step.

This plugin can set these global variables:

- `number_of_attachments` (int): The number of attachments that were extracted.
- `subject` (string): The subject of the email that had the attachment.
- `body` (string): The body of the email.
- `fileX` (string): *X* is a number from 1 to *number_of_attachments*.
- `from` (string): The email address in the *From* field of the message.
- `number_of_ccs` (int): The number of CC recipients.
- `ccX` (string): The email address of CC recipient *X*, where *X* is a number from 1 to *number_of_ccs*.

Version 1.0.3

Name	Type	Required	Description
host	string	true	Host name or IP address of the mail server to check. Default value is localhost.
username	string	true	User ID on the server.
password	string	true	Password that goes with username on the server.
port	string	false	TCP port for connecting to the server. Normally this is 110 for non-encrypted, 995 for SSL. Specify custom value as needed. Default value is 110.
trust	string	false	Set to "1" if all hosts should be trusted and certificates will not be checked. This option also forces the use of <code>com.sun.mail.util.MailSSLSocketFactory</code> as the <code>SSLSocketFactory</code> .
basedir	string	false	Location in which to save attachment files. Defaults to the temp directory as reported to Java by the OS at runtime (<code>java.io.tmpdir</code>).
attachment_prefix	string	false	Prefix this string to the attachment file name. This is needed if you expect collisions in file names.
ssl	string	false	If 1, then an encrypted connection will be attempted. Make sure to set the port property appropriately. Default value is 0.
delete_message	bool	false	If set to true, the fetched email will be marked as deleted. Default value is false.

Version 1.0.5

The POP3 File Reader Version 1.0.5 is available through the download link in the right-sidebar of this page. In addition to the above parameters, these parameters may be set:

Name	Type	Required	Description
trust	string	false	If 1, all hosts will be trusted and certificates will not be checked. This option also forces the use of <code>com.sun.mail.util.MailSSLSocketFactory</code> as the <code>SSLSocketFactory</code> .
delete_message	bool	false	If set to true, the fetched email will be marked as deleted. Default value is false.

Plugin

POP3 Client (.ZIP)

Related Articles

- [Creating an Email Message](#)
- [Customizations > Plug-ins](#)
- [Email Functions](#)
- [Email Target](#)
- [Plugins Available in Jitterbit Harmony](#)
- [POP3 File Reader](#)
- [Routing SOAP Faults to an Operation or Email](#)
- [Send Email with Attachment](#)

Related Topics

- [Apply Plug-ins \(Design Studio\)](#)
- [Plugin Library](#)
- [Plugins \(Cloud Studio\)](#)

Last updated: Apr 22, 2019